



Article published on March 9th 2012 | [Software](#)

Passwords are good but they can be easily forgotten. A forgotten password sometimes brings you troubles, even disasters. Luckily, there always exists some approaches to recover or reset a forgotten password. Here's a look at how to reset a forgotten Windows 7 password with an installation disc.

You might have been told to use a password reset disk or another admin account to reset a forgotten Windows 7 password. But for most users, these are useless when they get the Windows password forgotten. The password reset disk must be created before your password is forgotten while most users forgot the only administrator password. If you are one of those users, please try to use your installation disc instead. Don't have one? Still doesn't matter. Rekeysoft Windows Password Recovery is always available.

Reset Windows 7 password with an installation disc

By using this method, all you need is a copy of the Windows installation disk and Sticky Keys trick (an accessibility feature that allows a user to tap the Shift, Ctrl, Alt, or Windows key once to achieve the same effect as holding the key down).

1. Boot your computer from the installation disc.
2. After loading the setup files, select your language and click Next -> click the Repair your computer link on the Install Windows screen -> select the operating system to repair and click Next -> click Command Prompt to open a command prompt window.
3. On the command prompt, type "copy c:\windows\system32\sethc.exe c:" and press Enter. And then type "copy /y c:\windows\system32\cmd.exe c:\windows\system32\sethc.exe" and press Enter.
4. Reboot the computer. On the logon screen, tap Shift five times and you'll see an administrator mode command prompt.
5. Now you can reset the password. Just type "net user MyUserName MyNewPassword" (replace the MyUserName and MyNewPassword with the combination you want) and press Enter.
6. Exit the Command Prompt, and log into the computer using your new password.

Notes:

1. To prevent other users from using the same trick to reset your password, you put the original sethc.exe file back. Reboot your computer from the installation CD and then open the command prompt by taking steps above. Next type "copy /y c:\sethc.exe c:\windows\system32\sethc.exe" and press Enter.
2. By taking this method, you will lose access to encrypted files, encrypted email messages, and stored passwords for Internet Explorer and network resources. Remember to back up your important data regularly.

Reset Windows 7 password without a installation disc

Don't have an installation disc at hand? Don't worry! You still have opportunities to reset your forgotten Windows 7 password. That's to use Rekeysoft Windows Password Recovery. This Windows password reset app allows you to burn a bootable password reset CD/DVD/USB and reset the forgotten password instantly. 100% security is guaranteed.

1. Download and install Rekeysoft Windows Password Recovery in any other PC.
2. Burn a bootable Windows password reset disk with a CD/DVD or USB flash drive in seconds.
3. Boot the computer that you want to reset password of from the password reset CD/DVD/USB.
4. Reset your forgotten password to blank by following the instructions of DOS command prompt. This takes you only 1-2 minutes.
5. Reboot computer and log into your computer without password.

There is no need to worry about forgetting Windows 7 password. You can easily reset Windows 7 password by using its installation disc or Windows password recovery tool.

Article Source:

<http://www.articleside.com/software-articles/how-to-reset-windows-7-password-by-using-its-installation-disc.htm> - [Article Side](#)

[Cao Yao](#) - About Author:

You can easily a [reset Windows 7 password](#) with its installation disc or third-party a [Windows password recovery tool](#).

Article Keywords:

reset windows 7 password, installation disc

You can find more [free articles](#) on [Article Side](#). Sign up today and share your knowledge to the community! It is completely FREE!